


## SOFTWARE DOWNLOAD

Download the different software via our secure FTP server. Go to <https://www.cybelec.ch/>




- Click on **Contact -> FTP (1)**, Fill your **Username (2)**, Fill your **Password (3)** and Click on **Log in (4)** button.
- Click on **Offline Software -> Procedure (5)**, Click on the **Download link (6)** button to download the latest version of **FASTwareXXX\_Target Setup.exe** and save it on your PC.
- Click on **Offline Software -> Procedure -> VisiTouch 19 (7)** Click on the **Download link (8)** button to download the latest version of **VisiTouch 19 Press PS PC** and save it on your PC.

## SOFTWARE INSTALLATION

### FASTWARE

The FASTware license utility **must be installed and the license activated before installing VisiTouch Offline.**


Start the application **FASTwareXXX\_Target Setup.exe**. Make sure you run it (right-click) **AS AN ADMINISTRATOR.**



Select the **Language (1)**, Click on **Next > (2 and 3)**, Select **FASTware only, Full install (4)**, Click on **Next > (5)** and finish the installation. A pop-up will open, **close it and go to next page, chapter LICENSE REGISTRATION.**

### VISITOUCH OFFLINE

Start the application **VisiTouch\_19\_Press\_PS\_PC.exe**. Make sure you run it (right-click) **AS AN ADMINISTRATOR.**




Select the **Language (1)**, Click on **Next > (2 and 3)** and finish the installation. You can now use VisiTouch Offline.

**LICENSE REGISTRATION**

Start the program **FASTware basic appli (1)** located in:  
*Windows Start button -> FASTware 7 -> FAST Tools -> FASTware basic appli*



**Make sure you run it with administrator privileges.**

Click on **Licenses Window (2)** to open FW licenses management.



**VISITOUCH OFFLINE – TRIAL LICENSE**

➤ **Activate your product for 10 days**



Fill the field **FASTware serial number (7)** with the **FASTware S/N (5)** found on the Voucher.

Fill the field **Add a new license (10)** with the **FASTware Trial Use (6)** found on the Voucher.

Click on **Register new code (11)** button. A **pop-up (12)** will inform you that a new serial has been registered.

You can now install VisiTouch Offline software.

**VISITOUCH OFFLINE – LIFETIME LICENSE**

➤ **Activate your product for no limit duration time**

Send us by email at [sales.adm@cybelec.ch](mailto:sales.adm@cybelec.ch) these information: **Voucher S/N (3)**, **Security Code (4)** and **Computer ID (8)**.

You will receive by mail under 2-3 working days your Lifetime license code.

Fill the field **FASTware serial number (7)** and **Add a new license (10)** with the information provided.

Then, click on **Register new code (11)** button. A **pop-up (12)** will inform you that a new serial has been registered.